

MaxIm DL ASCOM Interface Cheat Sheet

Origin: extracted from SiTech/SitechEXE.pdb for PlaneWave STI v1.4.3 using dotPeek

MaxIm.Application Class

Methods:

Autofocus(object ExposureDuration): void
Blink(int Interval, object Images, object StartStop): void
CalAddBias(object FilePath): bool
AddDark(object FilePath): bool
CalAddFlat(object FilePath): bool
CalClear(): void
CalSet(): bool
CloseAll(): void
CompareImages(object LeftImage, object RightImage): void
LogMessage(string Text, object MessageType): void
SetCMYCoeffs(float CR, float CG, float CB, float MR, float MG, float MB, float YR,
float VG, float YB): void
SetRGBCoeffs(float RR, float GG, float BB): void
TileHorizontal(): void
TileVertical(): void

Properties:

AutofocusStatus: short
Blinking: bool
CalAutoFlat: bool
CalManualScale: float
CalMasterBias: object
CalMasterDark: object
CalMasterFlat: object
CalMedianBias: bool
CalMedianDark: bool
CalMedianFlat: bool
CalScaleType: short
CCDCamera: CCDCamera object
CurrentDocument: Document object
Documents: Document object
EventMask: int
FirstDocument: Document object
Focuser2Connected: bool
FocuserConnected: bool
LockApp: bool
NextDocument: Document object
TelescopeConnected: bool
Version: float

MaxIm.CCDDCamera Class

Methods:

AbortExposure(): void
CacheCurrentExposureSettings(): void
Calibrate(): void
Expose(double Duration, short Light, object Filter): bool
GuiderCalibrate(double Duration): bool
GuiderExpose(double Duration): bool
GuiderMove(GuiderDirectionType Direction, float Duration): bool
GuiderMoveStar(double X, double Y): bool
GuiderSetStarPosition(short X, short Y): void
GuiderStop(): bool
GuiderTrack(double Duration): bool
Quit(): void
RestoreCachedExposureSettings(): void
SaveImage(object FilePath): bool
SetFITSKey(object Key, object Value): bool
SetFullFrame(): void
ShowWindow(bool Show): void
StartDownload(): void
StartSequence(object SequenceFile): void

Properties

AmbientTemperature: double
AO7MirrorHome: bool
AO7TiltX: short
AO7TiltY: short
AO7TrackBoxCount: int
AOBumpTime: int
AOMirrorHome: bool
AOSwapMirrorAxes: bool
AOSwapMotorAxes: bool
AOTiltX: short
AOTiltY: short
AOTrackBoxCount: int
AutoDownload: bool
BinX: short
BinY: short
CameraName: string
CameraStatus: CameraStatusCode
CameraXSize: short
CameraYSize: short
CanSetTemperature: bool
CoolerOn: bool
CoolerPower: short

DisableAutoShutdown: bool
Document: Document
EventMask: int
Exposure Time: short
FanEnabled: bool
FastReadout: bool
Filter: short
FilterNames: object
FilterWheelName: string
FWHM: double
GuideControlVia: GuideViaType object
GuiderAggressiveness: short
GuiderAggressivenessX: float
GuiderAggressivenessY: float
GuiderAmbientTemperature: double
GuiderAngle: float
GuiderArray: object
GuiderAutoSelectStar: bool
GuiderCalState: int
GuiderCameraID: short
GuiderCanSetTemperature: bool
GuiderCoolerOn: bool
GuiderCoolerPower: short
GuiderDeclination: short
GuiderFanEnabled: bool
GuiderFilter: short
GuiderFilterNames: object
GuiderFilterWheelName: string
GuiderMaxMoveX: float
GuiderMaxMoveY: float
GuiderMinMoveX: float
GuiderMinMoveY: float
GuiderMoving: bool
GuiderName: string
GuiderNewMeasurement: bool
GuiderNumReadoutModes: short
GuiderNumSpeeds: short
GuiderOutputEnables: short
GuiderReadoutMode: short
GuiderReadoutModes: object
GuiderReverseX: bool
GuiderReverseY: bool
GuiderRunning: bool
GuiderSpeed: short
GuiderSpeeds: object
GuiderTemperature: double

GuiderTemperatureSetpoint: double
GuiderXError: float
GuiderXSize: short
GuiderXSpeed: float
GuiderXStarPosition: float
GuiderYError: float
GuiderYSize: short
GuiderYSpeed: float
GuiderYStarPosition: float
HalfFluxDiameter: double
HasFilterWheel: bool
HasShutter: bool
ImageArray: object
ImageReady: bool
LastGuiderError: string
LeaveOnCF: bool
LinkEnabled: bool
MainCameraID: short
MaxBinX: short
MaxBinY: short
MaxPixel: int
MaxPixelX: short
MaxPixelY: short
NumReadoutModes: short
NumSpeeds: short
NumX: short
NumY: short
PixelSizeX: double
PixelSizeY: double
PowerOfTwoBinning: bool
ReadoutMode: short
ReadoutModes: object
ReadyForDownload: bool
SequenceBaseFilename: string
SequenceNextIndex: short
SequenceRunning: bool
ShutterOpen: bool
Speed: short
Speeds: object
StartX: short
StartY: short
Temperature: double
TemperatureSetpoint: double
XYBinning: bool